Managing systemd Services

systemd is the central system and service manager in SUSE Linux Enterprise Server for NVIDIA used to control background daemons, system settings and operational targets. By using declarative unit files and the systemctl utility, systemd streamlines service administration, enables automated boot-time service execution and provides precise dependency tracking, allowing administrators to efficiently start, stop, enable and troubleshoot system services.

Prerequisites

- Basic understanding of Linux processes, daemons and control groups
- Understanding unit files

Publication Date: 12 Nov 2026

Contents

1 What is systemd? 3

2 Converting SysV init to systemd 3

3 Starting and stopping systemd services 6

4 Enabling and disabling systemd services 7

5 Sending termination signals to systemd services 8

6 Managing systemd targets with the **systemctl** command 9

7 Troubleshooting `systemd` management 11

8 Best practices for `systemd` management 12

9 **`systemctl`** commands overview 13

10 More information 15

11 Legal Notice 15

A GNU Free Documentation License 16

1 What is systemd?

systemd is a system and service manager for Linux operating systems. It is the default initialization system for major Linux distributions. systemd is not directly initiated by the user, but installed through the /sbin/init and started during the early boot. systemd acts as the init system that brings up and maintains user space services when run as the first process on boot (PID 1). PID 1 is known as *init* and is the first Linux user-mode process created. It runs until the system shutdown.

systemd owns PID 1, and is started directly by the kernel. All other processes are started directly by systemd or one of its child processes. systemd mounts the host's file system and manages temporary files. It is backward compatible with the SysV init scripts. SysV is an initialization system that predates systemd.

In systemd, a unit is a resource that the system knows how to operate on and manage. This is the primary object that the systemd tools use. These resources are defined with configuration files called unit files.

systemctl is the central management tool for controlling the init system. It is used to examine and control the state of the systemd system and service manager.

Targets in systemd are groups of related units that act as synchronization points during a system boot. Target unit files have a .target file extension. Target units group together various systemd units through a chain of dependencies.

For troubleshooting, you can use **journalctl**, which is used to query and display log messages from the systemd journal.

For more information on systemd, you can refer to https://systemd.io and **man 1 systemd**.

2 Converting SysV init to systemd

SysV init is the traditional initialization system used by older Linux distributions. It is often referred to as init. Converting a legacy SysV init script to a systemd service unit involves replacing a procedural shell script with a declarative configuration file. In the SysV model, services are managed via scripts in /etc/init.d/ using case statements to handle start, stop and restart actions. In systemd, unit files are used and located at /etc/systemd/system/ to define the service's behavior through key-value pairs.

1. Open your existing script in /etc/init.d/and look for the LSB (Linux Standard Base) header. This block contains the configuration you need for your new unit file.
2. Create a new .service file at /etc/systemd/system/ and use the gathered metadata.

3. Load and test the new service. Before finalizing, tell `systemd` to scan for the new file and then attempt to start it.
4. Create the `.service` unit file using the metadata you gathered.
5. Enable the new service at boot:

```
> sudo  systemctl enable NEW_SERVICE
```

You can now safely remove or move the old script from `/etc/init.d/` to prevent confusion.

In the following example, `boot.local` and `after.local` are used.

EXAMPLE 1: CONVERTING `boot.local` AND `after.local` TO `systemd`

The SysV init script files like `/etc/init.d/boot.local` and `/etc/init.d/after.local` were used for running custom commands or scripts at the end of the boot process.

In a `systemd` environment, to run your own startup script,we recommended creating a custom `systemd` service unit file. The `boot.local` script typically runs very early in the boot process, while `after.local` runs later, after most system services are up.

1. **Create the scripts:** Create script files with the commands and make them executable. For example:
   - For `boot.local` actions, create `/usr/local/bin/my.early-boot.sh`
   - For `after.local` actions, create `/usr/local/bin/my.late-boot.sh`
2. **Create the `systemd` unit files:** Create the `.service` unit files in the `/etc/systemd/system/` directory. For example:
   - For `boot.local`, this service should run before basic system initialization. Create a service file, `/etc/systemd/system/my-early-boot.service`:

```
[Unit]
  Description=My early startup script
  DefaultDependencies=no
  After=basic.target
  Before=basic.target sysinit.target shutdown.target

  [Service]
  Type=oneshot
  ExecStart=/usr/local/bin/my-early-boot.sh
  RemainAfterExit=yes
```

```
[Install]
WantedBy=basic.target
```

- `Type=oneshot` is suitable for scripts that run once and then exit.
- `DefaultDependencies=no` and `After/Before` ensures it runs at an equivalent time to `boot.local`.

- For `after.local`, this service should run later, typically when the multi-user environment is ready. If it depends on the network being up, add `After=network-online.target`. Create `/etc/systemd/system/my-late-boot.service:`:

```
[Unit]
  Description=My late startup script
  # Add After=network-online.target if your script needs network access
  After=multi-user.target

  [Service]
  Type=oneshot
  ExecStart=/usr/local/bin/my-late-boot.sh
  RemainAfterExit=yes

  [Install]
  WantedBy=multi-user.target
```

3. **Reload the `systemd` manager:** After creating the files, reload the `systemd` manager configuration and enable your new services to run at boot:

```
> sudo  systemctl daemon-reload
```

```
> sudo  systemctl enable my-early-boot.service
```

```
> sudo  systemctl enable my-late-boot.service
```

4. **Enable the services:** Enable your new services to run at boot:

```
> sudo  systemctl enable my-early-boot.service
```

```
> sudo  systemctl enable my-late-boot.service
```

5. **Verification:** To verify that your new services are working as expected:

```
> sudo  systemctl status my-early-boot.service
```

```
> sudo  systemctl status my-late-boot.service
```

The expected output is that both should show `Active: inactive (dead)` with a successful exit code, because they are `Type=oneshot` and execute only once.

`systemd` is now the default and only initialization system for .

3 Starting and stopping `systemd` services

You can start and stop `systemd` services by using units which are resources. The target units are service units, which have a `.service` suffix. For service management tasks, you do not have to add the `.service` because `systemd` knows that you want to execute a service.

To start and stop `systemd` services, use the following commands:

- To start a `systemd` service:

  ```
  > sudo  systemctl start SERVICE
  ```

- To check the status of a `systemd` service:

  ```
  > sudo  systemctl status  SERVICE
  ```

- To stop a currently running `systemd` service:

  ```
  > sudo  systemctl stop SERVICE
  ```

You can also use the following **`systemctl`** commands:

- Stops the service and then starts it. If the service is not running, it is started.

  ```
  > sudo  systemctl restart SERVICE
  ```

- Reloads the `systemd` service's configuration file without interrupting operations.

  ```
  >  systemctl reload SERVICE
  ```

- Reloads the service if it supports reloading, otherwise it restarts the service. If the service is not running, it is started.

  ```
  > sudo  systemctl reload-or-restart SERVICE
  ```

4 Enabling and disabling systemd services

You can enable and disable `systemd` services by using `units` which are resources.

To enable and disable `systemd` services, follow:

1. To enable a service at boot:

```
> sudo  systemctl enable SERVICE
```

   A symbolic link is created usually in `/lib/systemd/system` or `etc/systemd/system` pointing into the location on disk where `systemd`looks for autostart files. This is either in `/lib/systemd/system` or `/etc/systemd/system`, which is usually `/etc/systemd/system/EXAMPLE_TARGET.target`.
   For example:

```
> sudo  systemctl enable firewalld.service
      Created symlink /etc/systemd/system/dbus-org.fedoraproject.FirewallD1.service
 \u2192 /usr/lib/systemd/system/firewalld.service.
      Created symlink /etc/systemd/system/multi-user.target.wants/firewalld.service
 \u2192 /usr/lib/systemd/system/firewalld.service.
```

2. To disable a service from starting automatically:

```
> sudo  systemctl disable SERVICE
```

   This removes the symbolic link that indicates that the service should be started automatically.
   For example:

```
> sudo  systemctl disable firewalld.service
      Removed /etc/systemd/system/multi-user.target.wants/firewalld.service.
      Removed /etc/systemd/system/dbus-org.fedoraproject.FirewallD1.service.
```

3. To check the status of a service:

```
> sudo  systemctl status SERVICE
```

   For example:

```
> sudo  systemctl status firewalld.service
      \u25cf firewalld.service - firewalld - dynamic firewall daemon
      Loaded: loaded (/usr/lib/systemd/system/firewalld.service; enabled; vendor p>
      Active: active (running) since Wed 2024-01-31 01:36:36 EST; 1h 5min ago
      Docs: man:firewalld(1)
```

```
      Main PID: 965 (firewalld)
      Tasks: 2
      CGroup: /system.slice/firewalld.service
      \u2514\u2500965 /usr/bin/python3 -Es /usr/sbin/firewalld --nofork --nopid
```

Enabling or disabling a service does not start it in the current session. You can use **`start`** or **`stop`** to start or stop the service and enable or disable it at boot.

5 Sending termination signals to `systemd` services

Each service in `systemd` is categorized into a control group which makes it easy to identify all parent and child processes of a service. This enables you to send a signal to each of these processes. You can send a signal to a `systemd` service or to the individual processes that belong to a service.



Warning: Do not cancel the D-Bus service in a running system

The D-Bus service is the message bus for communication between `systemd` clients and the `systemd` manager that is running as PID 1. D-Bus is a stand-alone daemon and an integral part of the init infrastructure.

Terminating or restarting the D-Bus service is neither recommended nor supported. This breaks the `systemd` client and server communication and makes most of the `systemd` functions unusable.

The **`systemd-cgls`** command displays all processes that belong to a `systemd` service. It recursively shows the contents of the specific Linux control group hierarchy in a tree.

- Lists all control groups and their processes:

```
> systemd-cgls
```

- Displays all processes that belong to a particular service, for example: the `libvirtd.service` service:

```
> systemd-cgls -u libvirtd.service
```

- Sends a termination signal to the service:

```
> sudo systemctl kill SERVICE
```

- By default, the **`kill`** command sends the signal to `all` processes of the specified control group. You can restrict it to the `control` or the `main` process. The latter is, for example, useful to force a service to reload its configuration by sending `SIGHUP`:

```
> sudo systemctl kill -s SIGHUP --kill-who=main SERVICE
```

- Sends a different signal to a service with the `-s` option, such as `SIGKILL` (9):

```
> sudo systemctl kill -s 9 SERVICE
```

6 Managing `systemd` targets with the **`systemctl`** command

`systemd` targets are special unit files that describe a system or synchronization state. They are used to group units together in order or bring the system to a certain state, just like other init systems use runlevels. You can use the **`systemctl`** command to manage `systemd` targets.

Getting and setting the default target

`systemd` has a default target that is used when booting the system. To find the default target for your system:

```
> sudo systemctl get-default
  multi-user.target
```

You can also change the default target:

```
> sudo systemctl set-default graphical.target
```

Listing the available targets

To get the available targets on your system:

```
> sudo systemctl list-unit-files --type=target
           STATE                     VENDOR PRESET
         basic.target                 static   -
         blockdev@.target             static   -
         bluetooth.target             static   -
         boot-complete.target         static   -
         cryptsetup-pre.target        static   -
```

```
        cryptsetup.target             static   -
        ctrl-alt-del.target           alias    -
        cvs.target                    static   -
        default.target                alias    -
        emergency.target              static   -
        exit.target                   disabled disabled
        final.target                  static   -
        first-boot-complete.target    static   -
        getty-pre.target              static   -
        getty.target                  static   -
        .....
```

Multiple targets can be active at the same time. An active target is when `systemd` attempts to start all the units in a specific target. To see a list of the active targets:

```
> sudo systemctl list-units --type=target
        UNIT              LOAD   ACTIE SUB    DESCRIPTION                    >
  basic.target            loaded active active Basic System
  bluetooth.target        loaded active active Bluetooth Support
  cryptsetup.target       loaded active active Local Encrypted Volumes
  getty.target            loaded active active Login Prompts
  graphical.target        loaded active active Graphical Interface
  local-fs-pre.target     loaded active active Preparation for Local File Syste>
  local-fs.target         loaded active active Local File Systems
  multi-user.target       loaded active active Multi-User System
  network-online.target   loaded active active Network is Online
  network-pre.target      loaded active active Preparation for Network
  network.target          loaded active active Network
  nss-lookup.target       loaded active active Host and Network Name Lookups
  nss-user-lookup.target  loaded active active User and Group Name Lookups
  paths.target            loaded active active Path Units
  remote-fs.target        loaded active active Remote File Systems
  slices.target           loaded active active Slice Units
  snapd.mounts-pre.target loaded active active Mounting snaps
  .....
```

Isolating targets

You can start all the units associated with a target and stop all units that are not part of the dependency tree. For example, if you are using a graphical environment with an active `graphical.target` target, you can stop the graphical system and enable a multiuser command-line system by isolating the `multi-user.target` target. Since the `graphical.target` target depends on the `multi-user.target` target, all the graphical units are stopped.

To take a look at the dependencies of the target you are isolating:

```
> sudo systemctl list-dependencies multi-user.target
```

Output:

```
multi-user.target
  ○ ├─after-local.service
  ● ├─apparmor.service
  ○ ├─appstream-sync-cache.service
  ● ├─auditd.service
  ● ├─avahi-daemon.service
  ● ├─btrfsmaintenance-refresh.path
  ● ├─chronyd.service
  ● ├─cron.service
  ● ├─cups.path
  ● ├─dbus.service
  ● ├─fail2ban.service
  ● ├─firewalld.service
  ● ├─irqbalance.service
  ● ├─kbdsettings.service
  ● ├─libvirtd.service
  ● ├─mcelog.service
  ● ├─ModemManager.service
  ● ├─NetworkManager.service
  ● ├─nscd.service
  ● ├─plymouth-quit-wait.service
  ○ ├─plymouth-quit.service
  ● ├─postfix.service
```

You can isolate the specific target:

```
> sudo sudo systemctl isolate multi-user.target
```

7 Troubleshooting `systemd` management

If you are experiencing problems with `systemd`, try the following troubleshooting tips to identify and resolve issues:

Check the runtime status of a service

To find out the current runtime status of a service:

```
> sudo systemctl status SERVICE
```

Display all processes that belong to a particular service, for example: the `libvirtd.service` service:

```
> systemd-cgls -u libvirtd.service
```

Check the logs for your service with the `journalctl -u SERVICE` command

If you experience any issue with a `systemd` service, check the service's log. For example:

```
> sudo  journalctl -u my-custom-service.service
```

The command displays logs for the specified service, including any error messages, warnings or other relevant information. You can use these logs to identify and fix issues with the service.

8 Best practices for `systemd` management

To manage `systemd` services, try certain best practices that are equipped to handle different situations:

Check the runtime status of a service

To find out the current runtime status of a service:

```
> sudo systemctl status SERVICE
```

Use absolute path in your `systemd` unit file

Use an absolute path for executable files and required files, such as configuration files or scripts in your `systemd` unit file. `systemd` does not rely on the user's environment variables like `$PATH` to locate files. Use the *ExecSearchPath* directive in the `[SERVICE]` section.

```
[Service]
                ExecSearchPath=ABSOLUTE_PATH
```

Use the ExecReload directive

Use the *ExecReload* directive in the `[SERVICE]` section when you want to define a specific command that should be executed when you reload a service with the **`systemctl reload`** command. This is useful for services that can dynamically reload their configuration without a restart.

```
[Service]
ExecStart=PATH_TO_EXECUTABLE
ExecReload=PATH_TO_RELOAD_SCRIPT
```

Use the RestartSec directive

Use the *RestartSec* directive in the `[SERVICE]` section when you want to define a delay (in seconds) before the service is restarted after a failure. This is useful for services that require a specified time to release resources or prevent rapid restart loops that can cause high system load.

```
[Service]
ExecStart=PATH_TO_EXECUTABLE
```

```
Restart=on-failure
RestartSec=5
```

Disable emergency mode on a remote machine

You can disable emergency mode on a remote machine, for example, a virtual machine hosted on Google Cloud. If this mode is enabled, the machine is blocked from connecting to the network. For example:

```
> sudo systemctl mask emergency.service
```

```
> sudo systemctl mask emergency.target
```

9 `systemctl` commands overview

The **`systemctl`** command is used to examine and control the state of `systemd` and service manager.

You can use the following common **`systemctl`** commands and refer to the *man systemctl* page.

9.1 Viewing `systemd` information

To view information about `systemd` components, you can use the following commands:

systemctl list-units

Lists the `systemd` units. You can use the optional arguments: **`--state=running`** to show the active units and **`--type=service`** to show the exited and active units.

systemctl list-unit-files

Lists the `systemd` units and the status, such as static, generated, disabled, alias, masked, and enabled.

systemctl list-dependencies

Lists the dependency tree.

systemctl list-dependencies *`UNIT_FILE`*

Lists the dependencies of a unit file.

9.2 Managing `systemd` services

The **`systemctl`** command enables you to perform the following tasks with services.

systemctl status *SERVICE*

Checks the status of the specific service.

systemctl show *SERVICE*

Displays the service information.

systemctl start *SERVICE*

Instead of manually starting the service, use the **`start`** command. When a change is made to the configuration file, the related service must be started again.

systemctl stop *SERVICE*

Stops a specific running service.

systemctl restart *SERVICE*

Instead of manually restarting the service, use the **`restart`** command. When a change is made to the configuration file, the related service must be restarted again.

systemctl enable *SERVICE*

Enables the service on boot.

systemctl disable *SERVICE*

Disables the service on boot.

systemctl reload-or-restart *SERVICE*

Reload the service if it supports reloading, otherwise it restarts the service. If the service is not running, it is restarted.

systemctl mask *SERVICE*

When a service is masked, this means the unit file is symlinked to `/dev/null`. A symlink for a masked service is created from `/etc/systemd/system` to point to `/dev/null`. This makes it impossible to load the service even if another enabled service requires it. It must be stopped manually, or it continues to run in the background. You can use **`--runtime`** option to only mask temporarily until the next reboot of the system.

```
Created symlink /etc/systemd/system/FOSSLinux.service → /dev/null.
```

systemctl unmask *SERVICE*

Unmasks the service. It is effective when the system is started or restarted manually.

9.3 Managing system states

The **`systemctl`** command enables you to perform power management processes on your system, like restarting, shutting down and so on, as described below.

systemctl reboot

Reboots the system `reboot.target`.

systemctl poweroff

Powers off the system `poweroff.target`.

systemctl emergency

Goes into the emergency mode `emergency.target`.

systemctl default

Goes back to default target `multi-user.target`.

10 More information

- Man 1 systemd
- Man 1 journalctl
- Man 1 systemd-cgls
- Man 1 systemctl
- Man 5 systemd.service
- Man 5 systemd.kill
- Man 7 systemd.boot
- Introduction to `systemd` basics https://documentation.suse.com/smart/systems-management/html/systemd-basics/index.html
- System and Service Manager https://systemd.io/

11 Legal Notice

Copyright© 2006– 2026 SUSE LLC and contributors. All rights reserved.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or (at your option) version 1.3; with the Invariant Section being this copyright notice and license. A copy of the license version 1.2 is included in the section entitled “GNU Free Documentation License”.

For SUSE trademarks, see https://www.suse.com/company/legal/. All other third-party trademarks are the property of their respective owners. Trademark symbols (®, ™ etc.) denote trademarks of SUSE and its affiliates. Asterisks (*) denote third-party trademarks.

All information found in this book has been compiled with utmost attention to detail. However, this does not guarantee complete accuracy. Neither SUSE LLC, its affiliates, the authors, nor the translators shall be held liable for possible errors or the consequences thereof.

A GNU Free Documentation License

Copyright (C) 2000, 2001, 2002 Free Software Foundation, Inc. 51 Franklin St, Fifth Floor, Boston, MA 02110-1301 USA. Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or non-commercially. Secondarily, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image for-

mats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or non-commercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally

prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.

B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.

C. State on the Title page the name of the publisher of the Modified Version, as the publisher.

D. Preserve all the copyright notices of the Document.

E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.

F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.

G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.

H. Include an unaltered copy of this License.

I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.

J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.

K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.

L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.

M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.

N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.

O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties--for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See https://www.gnu.org/copyleft/.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

ADDENDUM: How to use this License for your documents

```
Copyright (c) YEAR YOUR NAME.
Permission is granted to copy, distribute and/or modify this document
under the terms of the GNU Free Documentation License, Version 1.2
or any later version published by the Free Software Foundation;
with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts.
A copy of the license is included in the section entitled “GNU
Free Documentation License”.
```

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the “with...Texts.” line with this:

```
with the Invariant Sections being LIST THEIR TITLES, with the
Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.
```

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.